




# Mobile App USER GUIDE





# Mobile App

## USER GUIDE

The Leviton Inform app provides remote monitoring of Leviton devices that feature Inform Technology — information such as intelligent voltage level sensing, liquid accumulation, ground continuity, enclosure temperature and more. The actual information available will vary by device.

For the LEV Series Mechanical Interlocks with Inform, the app allows remote monitoring of the following information:

- Phase voltage on the load and line side of switch
- Ground continuity monitoring
- Liquid accumulation detection
- Temperature and humidity levels inside the enclosure

## USER SUPPORT

**Tech Line:** 1-800-824-3005

Monday - Friday 8 AM - 10 PM ET

Saturday 9 AM - 7 PM ET

Sunday 9 AM - 5 PM ET

**Email:** [inform@leviton.com](mailto:inform@leviton.com)

**Website:** [leviton.com/inform](http://leviton.com/inform)

## TABLE OF CONTENTS

|                                      |          |
|--------------------------------------|----------|
| <b>GETTING STARTED .....</b>         | <b>3</b> |
| Registering a New Account.....       | 4        |
| <b>MANAGE ORGANIZATION</b>           |          |
| Set Up Organization .....            | 5        |
| <b>MANAGE USERS</b>                  |          |
| Manage Users.....                    | 9        |
| Adding Users.....                    | 10       |
| Editing a User's Permission Level... | 11       |
| Removing Users .....                 | 12       |
| <b>ALERT NOTIFICATION SYSTEM</b>     |          |
| Overview .....                       | 13       |
| Enable/Disable Notifications .....   | 14       |
| <b>MANAGE DEVICES</b>                |          |
| Add Device.....                      | 15       |
| Device Maintenance                   |          |
| • Edit Device Info .....             | 18       |
| • Reconfigure Wireless .....         | 19       |
| • Delete Device .....                | 20       |
| • Update Firmware .....              | 20       |
| <b>DEVICE HEALTH MONITORING</b>      |          |
| Overview .....                       | 21       |
| Main Screen.....                     | 21       |
| Status Symbols.....                  | 24       |
| • Warning.....                       | 24       |
| • Offline.....                       | 25       |
| • Fault.....                         | 25       |
| • Operating Details.....             | 26       |
| <b>ADDITIONAL FEATURES</b>           |          |
| Supporting Documentation.....        | 27       |

## GETTING STARTED

Before setting up and using the Inform™ Mobile App, perform the following tasks:

- Assign a primary account administrator for performing all setup tasks
- Gather a list of users (name and email address) who will be using the mobile app for your organization [administrator task]
- Download and install the Inform Mobile app from the App Store or Google Play
- Launch the app and create an account for your organization [administrator task]




Inform is also available as a desktop app.

This manual applies to the mobile app. However, the desktop version has all the same functionality as the mobile app, with one exception, the ability to enroll devices.

Access the Inform desktop app at:


[inform.leviton.com](http://inform.leviton.com)



**ADMINISTRATOR SET UP****Registering a New Account**

Prior to other actions such as setting up an organization, the administrator needs to create and register a new account:

- Administrator Name
- Administrator Email Address
- Administrator Password




**MANAGE ORGANIZATION**  
Administrator Task

Set Up Organization [administrator]



Upon first sign-in, you will be prompted to set up organization details:

- Company Name
- Email Address
- Street Address
- City, State, Zip
- Country



Next, you will be prompted to add your first device. During the initial setup, you will also be prompted to create a building and area

- You must create at least one building and area
- See section for “Add Devices” (page 15) for more detail






## Set Up Organization [administrator]

If you are not ready to add a device, you can still set up buildings and areas or add users




To set up buildings and areas:

- Select Organization from the main menu
- Select Buildings



## Set Up Organization [administrator]



- Set up buildings and areas (continued)
  - Tap on the “+” icon in the upper right corner
  - Enter Building Name, then tap Next
  - Enter Area Name, then tap Save
- Repeat to add more areas and buildings
- You can also edit building and areas names, or delete altogether



## Set Up Organization [administrator]

To view, add, edit or delete areas within buildings:

- Tap on the Building Name (from the list of Buildings)
- The list of Areas will appear
- Perform the desired function:
  - Tap on + ADD AREA to add new area
  - Tap on Area name to edit or delete








# MANAGE USERS

Administrator Task


## Manage Users [administrator]




Tap on the “≡” icon in the upper left corner of the screen; then select Users from the menu

- All users associated with the organization will be listed on the resulting page, along with status (pending or confirmed)



## Adding Users [administrator]


- Tap on the “” icon in the upper right-hand corner of the screen
- Enter email address of the user, and select permissions profile:
  - Admin – all app functions; can add/edit/delete buildings, areas, or users
  - Installer – all app functions; no ability to add/edit/delete buildings, areas, or users
- User accepts invitation
  - Click on link in email; enter name and password
  - Verify email address



EDIT USERS [ADMINISTRATOR]

Editing a User's Permission Level


- Tap on the user's name
- Tap on the settings icon
- Select User Type and Save



## EDIT USERS [ADMINISTRATOR]

## Removing Users

- Tap on the user's name
- Tap on the settings icon
- Tap on Remove and confirm



## ALERT NOTIFICATION SYSTEM


Whenever there is an operating state change, an alert is generated and will be sent to any user that has enabled the notification system in their profile


Examples of alerts include:


- Loss or restoration of voltage to the line or load side of a switch
- Loss or restoration of ground connection
- Erroneous absence or presence of voltage on any terminal

**NOTE:** Only email notifications are available at this time




### Fault (Ground Fault) - Pump Station 1 - Leviton Corporate Headquarters

 **noreply@leviton.com** <noreply@leviton.com>  
To: James Smith  
On: Friday, December 6, 2019 at 8:04 AM

 If there are problems with how this message is displayed, click here to view it in a web browser.



Hello, this is an automated notification from your Inform system letting you know that the device: **Pump Station 1** has entered **FAULT** state for **GROUND FAULT**.


  

Copyright © 2019 Leviton Manufacturing Co., Inc., All rights reserved.  
201 North Service Rd. • Melville, NY 11747

## Enable/Disable Notifications

Tap on the “☰” icon in the upper left corner of the screen; then select Notifications from the menu

- User can enable or disable the alert notification function



# MANAGE DEVICES

Wi-Fi Enabled Devices





## Add Device

Prior to adding a device, it must be properly installed and powered

Devices require access to the internet via a Wi-Fi connection

- Compatible with Wi-Fi® (IEEE 802.11 a/b/g/n networks) @ 2.4GHz and 5GHz with WPA or WPA2 security
  - Procure Wi-Fi SSID and password prior to adding device
- Not compatible with captive portals




Tap on the “+” icon in the upper right corner of the screen, and then select Add Device



### Add Device







- Follow on-screen prompts to connect the device to the Wi-Fi network
- When asked to name your device, provide a meaningful name that helps identify connected equipment and/or installed location

(Numbers 1 through 10 have been added to lower right of each screen shown to clearly illustrate progression)



**NOTE REGARDING SCREEN 3:** Devices are automatically set to “Pairing Mode” during initial installation. The reset step shown here is only required if reconfiguring the network.





DEVICE MAINTENANCE

Edit Device Info

Allows user to rename and/or reassign the location (building/area) of a device



- Select settings icon from lower left corner of device detail page
- Select Edit Device Info from menu
- Enter new information and Save



## DEVICE MAINTENANCE Reconfigure Wireless

Allows user to reassign the location (building/area) of a device

- Select settings icon from lower left corner of device detail page
- Select Reconfigure Wireless from menu
- Follow the on-screen prompts (same as “Add a Device” detailed on page 16)




**NOTE:** Reset Button is pressed for one (1) second and released.

DEVICE MAINTENANCE

Delete Device

Allows user to delete the remote monitoring feature of a device


- Select trash can icon from lower right corner of device detail page
- Confirm deletion



Update Firmware

When new firmware is available, users can download and install from the app

- Icon will show when firmware updates are available
- Tap on icon and confirm update when ready



# DEVICE HEALTH MONITORING

The Inform™ App provides remote monitoring of the operating status – or device health – of connected devices


- The first devices to be launched with remote monitoring capabilities will be the new LEV Series Mechanical Interlocks



## Main Screen

The startup screen will show a list of all connected Inform devices




- Each device summary tab contains a product image, device name, installed location, operating status, and Wi-Fi signal strength
- The list order is based on operating status, with devices showing a fault at the top and fully functioning devices near the bottom







## Main Screen

The list can be filtered to look at only devices in a specific operating status

- FAULT – requires immediate attention
- WARNING – requires attention when convenient
- NORMAL ON – devices powered up and switch turned to ON position
- NORMAL OFF – devices powered up and switch turned to OFF position



The list can also be filtered to look at only devices in a specific building or area



### Status Symbols



NORMAL device operation; load turned ON



NORMAL device operation; load turned OFF



WARNING; device functional but requires investigation



OFFLINE



FAULT condition; requires immediate attention


### STATUS SYMBOLS



#### WARNING

Functional error that doesn't hamper power delivery, but requires investigation

- Excessive moisture detected
- I2C communications fault (cannot communicate with Power Sense board)
- Serial communications fault (between Display Controller and Wi-Fi board)





**STATUS SYMBOLS**  
**OFFLINE**

Device is not communicating with the cloud


- Time stamp shows when device went OFFLINE
- Operating status shows last known status



**STATUS SYMBOLS**  
**FAULT**

Hard failure – requires immediate attention

- Loss of voltage on the Line or Load side of switch (individual phases)
- Loss of Ground
- Voltage present on Load side of switch when switch is open (turned OFF)



## Operating Details

All sensor outputs and device details are available for additional troubleshooting

- Actual voltage readings on the line and load side terminals
- Status of moisture sensor
- Status of neutral and ground sensors
- Switch position
- Temperature and Relative Humidity inside enclosure
- Location of device
- Firmware version information and serial numbers




## ADDITIONAL FEATURES

### Supporting Documentation

Any supporting documentation that is associated with the device's product detail page on Leviton.com will also be available from within the app

- Tap on data sheets tab from the device detail page



**CONTACT INFORMATION**

User Support

**Tech Line:** 1-800-824-3005

Monday - Friday 8 AM - 10 PM ET

Saturday 9 AM - 7 PM ET

Sunday 9 AM - 5 PM ET

**Email:** [inform@leviton.com](mailto:inform@leviton.com)

**Website:** [leviton.com/inform](http://leviton.com/inform)

**Leviton Manufacturing Co., Inc.**

201 N Service Rd, Melville, NY 11747

Telephone: 1-800-323-8920 • FAX: 1-800-832-9538